

## *Modules for automated testing/quality control*

Calculations are same GUI-based modules.


Consists of 14 modules:

<b>SFRplus</b>	<b>eSFR ISO</b>	<b>SFR</b>	<b>Wedge</b>
<b>Random</b>	<b>Log-f Contrast</b>	<b>Star</b>	<b>Distortion</b>
<b>Blemish</b>	<b>Uniformity</b>	<b>Colorcheck</b>	<b>Stepchart</b>
<b>Multitest</b>	<b>Dot Pattern</b>	<b>SFRreg</b>	<b>Checkerboard</b>

Modules can be run as:

- Executable – EXE
- Shared libraries
  - Windows: DLL, Linux: SO, Mac: Dylib
  - For use with C / C++ / Python / .NET / Labview

## IT 2: Block diagram




## IT 3: Setup 1

In IS or Master, Click **Settings** → **IT Options** and make sure you have the correct options.

Checking all boxes recommended.

### Interface:



### Imatest.ini file:

[api]

nomsg = 1

savedel = 1

passFail = C:\camera\ModelX-Spec.ini

sfrrefine = 1

## IT 4: Setup 2

3. Analyze the image file with GUI-based ***imatest Master***.
4. Click Save settings... and save the settings in a named file. Example: api\_control\_xxx.ini
5. The ini file is a readable text file that can be edited— to change file names when moving between computers, change settings, or remove irrelevant entries.

## *IT 5: DOS call to EXE*


Issue a DOS call from the calling program. Format:

[module].exe param-1 param-2 param-3 param-4 param-5

(The parameters are listed in the next page)

**Example:**


"C:\Program Files\Imatest\v4.5\IT\bin\sfrplus.exe"



## *IT 6: EXE Call parameters*

**EXE call:** [Module].exe param-1 param-2 param-3 param-4 param-5

Param	
1	-1 closes all figures after the run ends. (Normal operation) -2 keeps the DOS window open after the program terminates. -3 and -4 are similar to -1 and -2 but open the error log file
2	Image file name
3	Folder where the IT and other programs are located. e.g.: "c:\program files\imatest\IT\bin\"
4*	.ini file name. If omitted, it defaults to imatest.ini.
5*	folder where results are written. defaults to Results/ folder in the directory with image file.



## *IT 8: Pass Fail INI File – SFRplus 1/2*

Secondary Readouts are  
selected during SFRplus  
setup

For example:

Secondary\_readout\_1  
means MTF@0.250\*Nyquist

Secondary\_readout\_2  
means MTF@0.5\*Nyquist

### **[sfrplus]**

Secondary\_readout\_1\_center\_mean\_min = .69

Secondary\_readout\_1\_outer\_mean\_min = .5

Secondary\_readout\_2\_center\_mean\_min = .3

Secondary\_readout\_2\_outer\_mean\_min = .15

Rotation\_degrees\_max = 1.5

FOV\_degrees\_diagonal\_min = 67

Convergence\_angle\_max = 1.6

... continued ...

Center means <0.3 Field

Outer means  
≥0.3 Field

Tilt test



## ***IT 9: Pass Fail INI File – SFRplus 2/2***

Distortion Bars In Image	↘	<b>[sfrplus]</b> ... continued ...
Found all required ROIs	→	Horizontal_bars_OK_min = 1
Color demosaic proper	↗	All_Edge_IDs_detected = 1
		Bayer_decode = 1
		Mirrored_chart = 1
Don't allow flipped chart		
Don't allow too bright/dark	↘	
Don't allow oversaturated Image (non-linear clipping)	↘	Chart_mean_pixel_level_bounds = .3 .8
		Low_pixel_saturation_fraction_max = .3
		High_pixel_saturation_fraction_max = .3
Offset $\sqrt{X^2 + Y^2}$ max	↗	Chart_radial_pixel_shift_max = 18

## ***IT 10: Pass Fail INI File – Blemish Detect***

	<b>[blemish]</b>
Defect Pixels	Dead_pixels_max = 50
	Hot_pixels_max = 50
Optical Center	Optical_center_offset_max = 30
	Relative_illumination_worst_corner_pct_min = 29
Corner Difference	Relative_illumination_corner_diff_pct_max = 21
	Uniformity_RoverG_corners_pct_max = 10.8
Uniformity Ratios	Uniformity_BoverG_corners_pct_max = 13.9
	Blemish_size_pixels = 20 49
Blemishes	Blemish_maximum_count = 2 1

2 blemishes of 20 pixels allowed  
1 blemish of 49 pixels allowed  
More blemishes? FAIL!

## IT 11: Pass Fail Monitor


Run from main Iimatest window; supported by nearly all fixed & interactive modules. Preview of Pass/Fail results.

Main P/F indicator  
(**green for P**;  
**red for F**)

Image thumbnail

History or original  
results data structure

Parsed results with  
**FAIL**s on top



Pass/Fail Monitor for Iimatest

File View Edit Help

2 tests run: 0 Passed; 2 Failed

Blemish Detect Pass/Fail monitor

spot\_center\_lightened.jpg

Test 2: **FAIL - 3**

History Log (CSV format)

```
nTest, P/F, mm-dd HH:MM:SS, Module, File name
0002, FAIL-3, 01-26_09:09:16, Blemish Detect, spot_center_lightened.jpg
0001, FAIL-5, 01-26_09:08:52, Blemish Detect, blemish_7-synth_JPEG90.JPG
```

	Pass/Fail Measurement (sorted: FAILs on top)	Pass/Fail	Value	Limit type	Limit(s)
1	all_tests	<b>FAIL</b>			
2	Optical_center_offset	<b>FAIL</b>	-42.271 ... max		37.14
3	Blemishes_all	<b>FAIL</b>			
4	Blemishes	<b>FAIL</b>			
5	Dead_pixels	P	0	max	618
6	Dead_pixel_clusters	P	0	max	1
7	Hot_pixels	P	0	max	618
8	Relative_illumination_worst_corner_pct	P	52.4	min	29
9	Relative_illumination_corner_diff_pct	P	12.376	max	21
10	Uniformity_RoverG_corners_pct	P	1.16	max	10.8
11	Uniformity_BoverG_corners_pct	P	1.09	max	13.9
12	R_div_G_ctr_corner_diff_pct	P	1.1627	max	10
13	B_div_G_ctr_corner_diff_pct	P	6.4072	max	10
14	Center_R_div_G_unnorml	P	0.9928	limits	0.9 1.1
15	Center_B_div_G_unnorml	P	1.0154	limits	0.9 1.1

The Iimatest Pass/Fail monitor provides realtime pass/fail results from Iimatest modules. It can remain open while modules run. Pass/Fail measurements (but not values) must be hard-coded into Iimatest. Please contact us if you need a measurement added.

Help Close

## *IT 12: JSON Output Format*

Imatest outputs files in JSON format:

```
{
  "Json Files" :
    { "Are easy to read" : ["by a human",
                           "by a computer program"],
      "Are better than" : ["CSV", "XML",
                           "Reading plots"]
    }
  "Strings"      : "Asdf",
  "Objects"      : { "Key" : "Value",    "foo" : "bar" },
  "Arrays"       : [0, 1, 2, 3, 4, 5],
}
```

JSON files can be easily processed by most programming languages. See <http://www.json.org> .

## Inside SFRplus Outputs

```
"passfail": {  
  "started_at": "2012-09-18 21:48:11",  
  "part_number": "720Pcam",  
  "serial_number": "123",  
  "ended_at": "2012-09-18 21:48:13",  
  "all_tests_passed": [1],  
  "Rotation_degrees_max": [1],  
  "Rotation_degrees": [0.1544402431],  
  "Rotation_degrees_passed": [1],  
  "FOV_degrees_diagonal_min": [65],  
  "FOV_degrees_diagonal": [71.48887417],  
  "FOV_passed": [1],  
  "Convergence_angle_max": [1],  
  "Horizontal_convergence_angle_degrees": [0.1962654529],  
  "Horizontal_convergence_angle_passed": [1],  
  "Vertical_convergence_angle_degrees": [-0.1782540181],  
  "Vertical_convergence_angle_passed": [1],  
  "Secondary_readout_1_center_mean_min": [0.69],  
  "Secondary_readout_1_center_name": "MTF @ 0.125 C/P",  
  "Secondary_readout_1_center_mean": [0.7605115781],  
  "Secondary_readout_1_center_mean_passed": [1],  
  "Secondary_readout_1_outer_mean_min": [0.5],  
  "Secondary_readout_1_outer_name": "MTF @ 0.125 C/P",  
  "Secondary_readout_1_outer_mean": [0.6414709955],  
  "Secondary_readout_1_outer_mean_passed": [1],  
  "Secondary_readout_2_center_mean_min": [0.3],  
  "Secondary_readout_2_center_name": "MTF @ 0.250 C/P",  
  "Secondary_readout_2_center_mean": [0.4810220612],  
  "Secondary_readout_2_center_mean_passed": [1],  
  "Secondary_readout_2_outer_mean_min": [0.15],  
  "Secondary_readout_2_outer_name": "MTF @ 0.250 C/P",  
  "Secondary_readout_2_outer_mean": [0.3197757488],  
  "Secondary_readout_2_outer_mean_passed": [1]  
}
```

## Inside Blemish Outputs

```
"passfail": {  
  "started_at": "2014-06-13 21:44:05",  
  "part_number": "1080Pcam",  
  "serial_number": "123",  
  "ended_at": "2014-06-13 21:44:07",  
  "all_tests_passed": [1],  
  "Dead_pixels_max": [300],  
  "Dead_pixels": [2],  
  "Dead_pixels_passed": [1],  
  "Hot_pixels_max": [300],  
  "Hot_pixels": [0],  
  "Hot_pixels_passed": [1],  
  "Optical_center_offset_max": [90],  
  "Optical_center_offset": [-20.73147695,-2.589069404],  
  "Optical_center_offset_radial": [20.89252059],  
  "Optical_center_offset_passed": [1],  
  "Relative_illumination_worst_corner_pct_min": [27],  
  "Relative_illumination_worst_corner_pct": [37.4989815],  
  "Relative_illumination_worst_corner_passed": [1],  
  "Relative_illumination_corner_diff_pct_max": [31],  
  "Relative_illumination_corner_diff_pct": [4.813874468],  
  "Relative_illumination_corner_diff_pct_passed": [1],  
  "Uniformity_RoverG_corners_pct_max": [13.9],  
  "Uniformity_RoverG_corners_pct": [1.87],  
  "Uniformity_RoverG_corners_pct_passed": [1],  
  "Uniformity_BoverG_corners_pct_max": [13.9],  
  "Uniformity_BoverG_corners_pct": [1.17],  
  "Uniformity_BoverG_corners_pct_passed": [1],  
  "Blemishes_detected_pixel_size": null,  
  "Blemishes_passed": [1,1],  
  "Blemish_size_pixels": [49,49],  
  "Blemish_maximum_count": [2,1],  
  "Blemishes_all_passed": [1]  
}
```

The Imatest IT image acquisition library, called through the Imatest IT shared library, allows you to use all Imatest IS supported acquisition interfaces

See [imatest.com/acquire](http://imatest.com/acquire) for all supported hardware

### **Show supported devices:**

```
list_devices(int nargout, mxArray &devices);
```



### **Acquire image from device:**

```
acquire_image(int nargout, mxArray &im_orig, mxArray &vstr, const  
mxArray &source_id, const mxArray &varargin);
```



## Manufacturing Test Interface

- Simple Pass/Fail GUI for Imatest IT
- Integrate with factory control & automated test equipment
- Open source project written in MFC C++
- To be ported to cross-platform GUI framework in future (QT, GTK or Java)



## *Thank You For Attending Our Class!*

We appreciate you attending our class and look forward to working with you.

Get in touch with us:

[support@imatest.com](mailto:support@imatest.com)

[sales@imatest.com](mailto:sales@imatest.com)

[charts@imatest.com](mailto:charts@imatest.com)

[testing@imatest.com](mailto:testing@imatest.com)

[training@imatest.com](mailto:training@imatest.com)

Software feature requests & issues

Purchasing and payment

Chart customization and questions

Equipment, test lab setup and automation

On-site training

Best Regards,

-The Imatest Team

End

Fin

Ende

結束

끝

終わり