



IT (Industrial Testing)

Modules for automated testing/quality control

Calculations are same GUI-based modules.

Consists of 14 modules:

SFRplus	eSFR ISO	SFR	Wedge
Random	Log-f Contrast	Star	Distortion
Blemish	Uniformity	Colorcheck	Stepchart
Multitest	Dot Pattern		

Modules can be run as:

- Executable – EXE
- Shared libraries
 - Windows:DLL, Linux:SO, Mac:Dylib
 - For use with C / C++ / Python / .NET / Labview


Feb 2016

Imatest 2 day class VII www.imatest.com ©2008-2016, Imatest LLC

P. VII-1



IT 2: Block diagram



Feb 2016

Imatest 2 day class VII www.imatest.com ©2008-2016, Imatest LLC

P. VII-2




IT 3: Setup 1

In IS or Master, Click **Settings** → **IT Options** and make sure you have the correct options.

Checking all boxes recommended.

Interface:



Imatest.ini file:

```
[api]
nomsg = 1
savedel = 1
passFail = C:\camera\ModelX-Spec.ini
sfrrefine = 1
```

Feb 2016

Imatest 2 day class VII www.imatest.com ©2008-2016, Imatest LLC

P. VII-3



IT 4: Setup 2

3. Analyze the image file with GUI-based **Imatest Master**.
4. Click Save settings... and save the settings in a named file. Example: api_control_xxx.ini
5. The ini file is a readable text file that can be edited— to change file names when moving between computers, change settings, or remove irrelevant entries.

Feb 2016

Imatest 2 day class VII www.imatest.com ©2008-2016, Imatest LLC

P. VII-4



IT 5: DOS call to EXE


Issue a DOS call from the calling program. Format:

[module].exe param-1 param-2 param-3 param-4 param-5

(The parameters are listed in the next page)

Example:

"C:\Program Files (x86)\Imatest\v4.4\IT\bin\sfrplus.exe"



Feb 2016

Imatest 2 day class VII www.imatest.com ©2008-2016, Imatest LLC

P. VII-5



IT 6: EXE Call parameters


EXE call: [Module].exe param-1 param-2 param-3 param-4 param-5

Param	
1	-1 closes all figures after the run ends. (Normal operation) -2 keeps the DOS window open after the program terminates. -3 and -4 are similar to -1 and -2 but open the error log file
2	Image file name
3	Folder where the IT and other programs are located. e.g.: "c:\program files\imatest\IT\bin\"
4*	.ini file name. If omitted, it defaults to imatest.ini.
5*	folder where results are written. defaults to Results/ folder in the directory with image file.

Feb 2016

Imatest 2 day class VII www.imatest.com ©2008-2016, Imatest LLC

P. VII-6



imatest® *IT 8: Pass Fail INI File – SFRplus 1/2*

Secondary Readouts are selected during SFRplus setup

For example:
Secondary_readout_1 means MTF@0.250*Nyquist

Secondary_readout_2 means MTF@0.5*Nyquist

... continued ...

[sfrplus]
 Secondary_readout_1_center_mean_min = .69
 Secondary_readout_1_outer_mean_min = .5
 Secondary_readout_2_center_mean_min = .3
 Secondary_readout_2_outer_mean_min = .15
 Rotation_degrees_max = 1.5
 FOV_degrees_diagonal_min = 67
 Convergence_angle_max = 1.6

Center means <0.3 Field

Outer means >=0.3 Field

Tilt test

Feb 2016 Imatest 2 day class VII www.imatest.com ©2008-2016, Imatest LLC P. VII-8



IT 9: Pass Fail INI File – SFRplus 2/2

[sfrplus] ... continued ...

- Distortion Bars In Image → Horizontal_bars_OK_min = 1
- Found all required ROIs → All_Edge_IDs_detected = 1
- Color demosaic proper → Bayer_decode = 1
- Mirrored_chart = 1
- Don't allow flipped chart
- Don't allow too bright/dark → Chart_mean_pixel_level_bounds = .3 .8
- Don't allow oversaturated Image (non-linear clipping) → Low_pixel_saturation_fraction_max = .3
- High_pixel_saturation_fraction_max = .3
- Offset $\text{Sqrt}(X^2 + Y^2)$ max → Chart_radial_pixel_shift_max = 18

Feb 2016

Imatest 2 day class VII www.imatest.com ©2008-2016, Imatest LLC

P. VII-9



IT 10: Pass Fail INI File – Blemish Detect

[blemish]

- Defect Pixels → Dead_pixels_max = 50
- Hot_pixels_max = 50
- Optical Center → Optical_center_offset_max = 30
- Relative_illumination_worst_corner_pct_min = 29
- Corner Difference → Relative_illumination_corner_diff_pct_max = 21
- Uniformity_RoverG_corners_pct_max = 10.8
- Uniformity Ratios → Uniformity_BoverG_corners_pct_max = 13.9
- Blemish_size_pixels = 20 49
- Blemishes → Blemish_maximum_count = 2 1

2 blemishes of 20 pixels allowed
1 blemish of 49 pixels allowed
More blemishes? FAIL!

Feb 2016

Imatest 2 day class VII www.imatest.com ©2008-2016, Imatest LLC

P. VII-10



IT 11: Pass Fail Monitor


Run from main ImaTest window; supported by nearly all fixed & interactive modules. Preview of Pass/Fail results.

Main P/F indicator
(green for P;
red for F)

Image thumbnail

History or original
results data structure

Parsed results with
FAILs on top



Feb 2016

Imatest 2 day class VII www.imatest.com ©2008-2016, ImaTest LLC

P. VII-11



IT 12: JSON Output Format

Imatest outputs files in JSON format:

```
{
  "Json Files" :
  {
    "Are easy to read" : ["by a human",
                          "by a computer program"],
    "Are better than" : ["CSV", "XML",
                          "Reading plots"]
  }
  "Strings" : "Asdf",
  "Objects" : { "Key" : "Value", "foo" : "bar" },
  "Arrays" : [0, 1, 2, 3, 4, 5],
}
```

JSON files can be easily processed by most programming languages. See <http://www.json.org>.

Feb 2016

Imatest 2 day class VII www.imatest.com ©2008-2016, ImaTest LLC

P. VII-12



IT 13: JSON Test Results

Inside SFRplus Outputs

```
"passfail": {
  "started_at": "2012-09-18 21:48:11",
  "part_number": "720Pcam",
  "serial_number": "123",
  "ended_at": "2012-09-18 21:48:13",
  "all_tests_passed": [1],
  "Rotation_degrees_max": [1],
  "Rotation_degrees": [0.1544402431],
  "Rotation_degrees_passed": [1],
  "FOV_degrees_diagonal_min": [65],
  "FOV_degrees_diagonal": [71.48887417],
  "FOV_passed": [1],
  "Convergence_angle_max": [1],
  "Horizontal_convergence_angle_degrees": [0.1962654529],
  "Horizontal_convergence_angle_passed": [1],
  "Vertical_convergence_angle_degrees": [-0.1782540181],
  "Vertical_convergence_angle_passed": [1],
  "Secondary_readout_1_center_mean_min": [0.69],
  "Secondary_readout_1_center_name": "MTF @ 0.125 C/P",
  "Secondary_readout_1_center_mean": [0.7605115781],
  "Secondary_readout_1_center_mean_passed": [1],
  "Secondary_readout_1_outer_mean_min": [0.5],
  "Secondary_readout_1_outer_name": "MTF @ 0.125 C/P",
  "Secondary_readout_1_outer_mean": [0.6414709955],
  "Secondary_readout_1_outer_mean_passed": [1],
  "Secondary_readout_2_center_mean_min": [0.3],
  "Secondary_readout_2_center_name": "MTF @ 0.250 C/P",
  "Secondary_readout_2_center_mean": [0.4810220612],
  "Secondary_readout_2_center_mean_passed": [1],
  "Secondary_readout_2_outer_mean_min": [0.15],
  "Secondary_readout_2_outer_name": "MTF @ 0.250 C/P",
  "Secondary_readout_2_outer_mean": [0.3197757488],
  "Secondary_readout_2_outer_mean_passed": [1]
}
```

Inside Blemish Outputs

```
"passfail": {
  "started_at": "2014-06-13 21:44:05",
  "part_number": "1080Pcam",
  "serial_number": "123",
  "ended_at": "2014-06-13 21:44:07",
  "all_tests_passed": [1],
  "Dead_pixels_max": [300],
  "Dead_pixels": [2],
  "Dead_pixels_passed": [1],
  "Hot_pixels_max": [300],
  "Hot_pixels": [0],
  "Hot_pixels_passed": [1],
  "Optical_center_offset_max": [90],
  "Optical_center_offset": [-20.73147695, -2.589069404],
  "Optical_center_offset_radial": [20.89252059],
  "Optical_center_offset_passed": [1],
  "Relative_illumination_worst_corner_pct_min": [27],
  "Relative_illumination_worst_corner_pct": [37.4989815],
  "Relative_illumination_worst_corner_passed": [1],
  "Relative_illumination_corner_diff_pct_max": [31],
  "Relative_illumination_corner_diff_pct": [4.813874468],
  "Relative_illumination_corner_diff_pct_passed": [1],
  "Uniformity_RoverG_corners_pct_max": [13.9],
  "Uniformity_RoverG_corners_pct": [1.87],
  "Uniformity_RoverG_corners_pct_passed": [1],
  "Uniformity_BoverG_corners_pct_max": [13.9],
  "Uniformity_BoverG_corners_pct": [1.17],
  "Uniformity_BoverG_corners_pct_passed": [1],
  "Blemishes_detected_pixel_size": null,
  "Blemishes_passed": [1],
  "Blemish_size_pixels": [49,49],
  "Blemish_maximum_count": [2,1],
  "Blemishes_all_passed": [1]
}
```

Feb 2016

Imatest 2 day class VII www.imatest.com ©2008-2016, Imatest LLC

P. VII-13



IT 12: Acquire Image Routine

The Imatest IT image acquisition library, called through the Imatest IT shared library, allows you to use all Imatest IS supported acquisition interfaces

See imatest.com/acquire for all supported hardware

Show supported devices:

```
list_devices(int nargsout, mxArray &devices);
```

Acquire image from device:

```
acquire_image(int nargsout, mxArray &im_orig, mxArray &vstr, const
mxArray &source_id, const mxArray &varargin);
```

Feb 2016

Imatest 2 day class VII www.imatest.com ©2008-2016, Imatest LLC

P. VII-14




IT 13: Operator Console



Manufacturing Test Interface

- Simple Pass/Fail GUI for Imatest IT
- Integrate with factory control & automated test equipment
- Open source project written in MFC C++
- To be ported to cross-platform GUI framework in future (QT, GTK or Java)



Feb 2016

Imatest 2 day class VII www.imatest.com ©2008-2016, Imatest LLC

P. VII-15



Thank You For Attending Our Class!

We appreciate you attending our class and look forward to working with you.

Get in touch with us:

support@imatest.com
sales@imatest.com
charts@imatest.com
testing@imatest.com
training@imatest.com

Software feature requests & issues
 Purchasing and payment
 Chart customization and questions
 Equipment, test lab setup and automation
 On-site training

Best Regards,

-The Imatest Team

End Fin Ende 结束 끝 終わり

Feb 2016

Imatest 2 day class VII www.imatest.com ©2008-2016, Imatest LLC

P. VII-16